

NAT Quick Guide

Static NAT configuration:

```
R1#int f0/0  
R1#ip nat outside  
R1#int f1/0  
R1#ip nat inside  
R1#ip nat inside source static 10.0.1.10 203.0.113.3
```

Dynamic NAT configuration:

```
R1#int f0/0  
R1#ip nat outside (faces internet)  
R1#int f2/0  
R1#ip nat inside (faces desktop pcs)
```

Then we need to configure the pool of global addresses...

```
R1#ip nat pool Flackbox 203.0.113.4 203.0.113.14 netmask 255.255.255.240
```

We need to create an access list which references the internal IP addresses we want to translate...

```
R1#access-list 1 permit 10.0.2.0 0.0.0.255
```

We need to associate the access list with the NAT pool to complete the configuration...

```
R1#ip nat inside source list 1 pool Flackbox
```

Or...

```
R1#ip nat inside source list 1 pool Flackbox overload (PAT Configuration)
```

To verify...

```
R1#show ip nat translation
```

```
R1#show ip nat statistics
```

```
R1#debug ip icmp
```

```
R1#debug ip nat
```

***Note: use the below command to remove translations from the translation table and can be used with troubleshooting...**

```
R1#clear ip nat translation (removes dynamic translations. Use )
```

PAT with Single IP Address config:

```
R1#int f0/0
```

```
R1#ip address dhcp
```

```
R1#ip nat outside
```

```
R1#int f1/0
```

```
R1#ip nat inside
```

```
R1#access-list 1 permit 10.0.2.0 0.0.0.255
```

```
R1#ip nat inside source list 1 interface f0/0 overload
```