


GO! Qube 8" Flight Plan Throw Quilt

Finished Size: 40" x 48"



Fabrics provided by Island Batik.

Dies Needed:

GO! Qube Mix & Match 8" Block (55776)

- GO! Square-4-1/2" (4" Finished) (Shape 1)
- GO! Half Square Triangle-4" Finished Square (Shape 3)
- GO! Half Square Triangle-2" Finished Square (Shape 5)
- GO! Rectangle-2-1/2" x 4-1/2" (2" x 4" Finished) (Shape 8)

GO! Qube 8" Companion Set – Angles (55789)

- GO! Trapezoid 45°-1-15/16"H x 6-3/8"W Cut (4" Finished Square) (Shape 16)

Additional Dies Needed

- GO! Strip Cutter-2-1/2" (2" Finished) (55014 or 55017)
- GO! Airplanes (55366)

Fabric Requirements:

Fabric Color	Total Yardage
White	1-1/2 yards
Blue	1 yard
Green	1/2 yard
Red	1/8 yard
Yellow	1/8 yard
Black	4" x 10"
Batting	50" x 58"
Backing	50" x 58"
Fusible	1-1/2 yards

NOTE: Apply fusible to back of appliqué fabrics according to manufacturer's instructions before cutting shapes.

Cut & Shift™ method to save fabric when cutting angled shapes: Start at one end of fabric, place over the shape, layer fabric if desired. Continue to cut and shift the fabric strip downward to align cut angle of fabric with angle of blades to cut the next trapezoid across the width of fabric.

Cutting Directions:


Fabric Color	Die	Number of Shapes to Cut
White	GO! Square-4-1/2" (4" Finished) (Shape 1)	Cut 6—5" x width of fabric (WOF) strips. Fanfold into 5" widths. Sub cut into 48—4" square finished.
White	GO! Half Square Triangle-4" Finished Square (Shape 3)	Cut 2—5-3/8" x WOF strips. Fanfold into 5-3/8" widths. Sub cut into 24—4" finished half square triangle (HST).
Blue	GO! Trapezoid 45°-1-15/16"H x 6-3/8"W Cut—4" Finished Square (Shape 16)	Cut 2—5-3/4" x WOF strips. Use Cut & Shift method. Sub cut into 24—4" finished trapezoids.
Blue	GO! Rectangle-2-1/2" x 4-1/2" (2" x 4" Finished) (Shape 8)	Cut 2—5" x WOF strips. Fanfold into 5" widths. Sub cut into 27—2" x 4" finished rectangles.
Green	GO! Half Square Triangle-2" Finished Square (Shape 5)	Cut 1—3-3/4" WOF strip. Fanfold into 3" widths. Sub cut into 24—2" finished HST.
Green	GO! Rectangle-2-1/2" x 4-1/2" (2" x 4" Finished) (Shape 8)	Cut 2—5" x WOF strips. Fanfold into 5" widths. Sub cut into 27—2" x 4" finished rectangles.
Red	GO! Airplanes (56366)	Cut 6 bi-planes.
Yellow	GO! Airplanes (56366)	Cut 6 airplanes and 6 propellers.
Black	GO! Airplanes (56366)	Cut 6 windshields and 6 motors.

Sewing Directions:


Press all seams open and use $\frac{1}{4}$ " seams, unless otherwise indicated.

Blocks:


1. Sew one blue 4" finished trapezoid (Shape 16) and one green 2" finished half square triangle (HST) (Shape 5) together as shown. Make 24 blue/green units.



2. Sew one white 4" finished HST (Shape 3) and blue/green unit together as shown. Make 24—4" finished trapezoid units.




3. Sew two 4" finished trapezoid units together as shown. Make 12—4" x 8" finished Chevron blocks.




4. Sew one white 4" finished square (Shape 1) to one white 4" finished square together as shown. Press seams to one side. Make 24—2-patch units.



5. Sew one white 2-patch unit to one white 2-patch unit together as shown. Spin seams in opposite directions. Make 12—8" x 8" finished 4-patch blocks.




6. Sew one blue 2" x 4" finished rectangle (Shape 8) to one green 2" x 4" finished rectangle (Shape 8) together as shown. Make 12—4" finished rectangle blocks.




Assemble the Quilt Top


1. Sew 3 chevron blocks and 3—4-patch blocks together as shown. Press to 4-patch blocks. Make 4 chevron rows.



2. Sew 9 rectangle blocks together as shown. Press seams to one side. Make 3 rectangle rows.



3. Sew chevron and rectangle rows together as shown. Press seams to one side.



4. Measure quilt top to bottom. Cut 2 border strips to that length. Sew border strips to right and left sides of quilt center. Press to borders.
5. Measure quilt top right to left. Cut 2 border strips to that length. Sew border strips to top and bottom of quilt center. Press to borders.
6. Apply airplane shapes onto quilt top as shown.

Airplane Appliqué

The airplanes will be appliquéd onto the pieced quilt blocks. The airplanes and bi-planes will be stitched onto the white 4-patch blocks as shown. Detailed instructions are included with the free machine embroidery download from www.accuquilt.com/airplanes55366.

Quilting and Finishing

1. Layer batting between quilt top and backing.
2. Pin or baste layers together.
3. Quilt as desired.
4. Add binding, mitering corners.

