
PRESS ON PANEL QUILT











FINISHED QUILT SIZE 38" × 57"

Please read all instructions before beginning this project. Yardage calculated using a 42" usable width of fabric. Pattern designed by Janet Wecker Frisch.

GENERAL INSTRUCTIONS

Please check www.rileyblakedesigns.com/ pattern-updates or scan the QR Code for any revisions before starting this project. This pattern requires a basic knowledge of quilting techniques and terminology. The quilt and block diagrams portrayed are



virtual images. The layout and look of your project may differ when using actual fabric. It is not recommended to prewash fabric before cutting and assembling.

Always verify your panel size before beginning. If your panel measurements differ from those given in the pattern, trim to the desired size or use coping strips to alter the size of your panel. If coping strips are needed, add oversized, coordinating strips of fabric to the necessary edges of the panel, then trim to the size specified in the pattern.

WOF = Width of Fabric RST = Right Sides Together LOF = Length of Fabric

FABRIC REQUIREMENTS

All fabrics from the [Fabric Name] collection unless stated otherwise.

(1) PD15250-PANEL Press On Main Panel

3 yard C15262-BLACK Pinstripe Plaid

1 3 yards C15256-WHITE Cord Stripe

3 yard C15263-BLACK Ironing Board Stripe (Binding)

OTHER SUPPLIES

Basic Sewing Supplies 2 ¼ yards Wide Back backing fabric of your choice Batting

CUTTING INSTRUCTIONS

When cutting fabrics, use a straight edge ruler and rotary cutter. Measurements include ¼" seam allowance. Label, allocate, and organize all cuts as noted.



Press On Panel

Fussy cut (1) panel 24" × 43", centered over the motif.*

*Note: If the panel motif reaches the edge of the cut, add coping strips first and then trim to the required size once the strips are added.



Black Pinstripe Plaid

Cut (4) 2 $\frac{1}{2}$ " × WOF strip. Sew together end-to-end then subcut:

- (2) 2 $\frac{1}{2}$ " × 43" strips. Label as A for inner side borders.
- (2) 2 ½" × 28" strips. Label as B for inner top/bottom borders.



White Cord Stripe

Cut (4) 5 ½" × LOF strip; subcut:

- (2) 5 $\frac{1}{2}$ " × 60" strips. Label as C for outer side borders.
- (2) 5 $\frac{1}{2}$ " × 42" strips. Label as D for outer top/bottom borders.



Black Ironing Board

Cut (5) 2 ½" × WOF strips. Set aside for binding.

SEWING TECHNIQUES

Sew all seams RST and with a ½" seam allowance unless stated otherwise. Refer to the quilt layout diagram for placement of the prints. Press seams as desired unless stated otherwise. Dimensions listed in steps are unfinished sizes. Please refer to the following general sewing techniques as these methods are referenced throughout the pattern in their abbreviated form.


QUILT ASSEMBLY

1. Follow the diagram to sew the **A**-strips to each side of the panel. Sew the **B**-strips to the top and bottom. The quilt center should measure 28" × 47".




28" × 47"

- 2. Measure and mark the center of each edge of the quilt center and ¼" from each corner.
- 3. Measure and mark the center of each **C** and **D**-strip.
- 4. Match the center of (1) **C**-strip to one side of the quilt center, RST, then pin the border strip in place. Sew the outer border strip to the quilt top between the two ¼" marks on the quilt center, backstitching at each end. Repeat to add an outer border strip to each side of the quilt center as shown. Press toward each outer border.



- 5. Fold the quilt center diagonally, WST, leaving the ends of the outer border strips perpendicular and press. Pull the vertical border away from the horizontal border. Use a ruler with a 45° angle to measure ¼" away from the marked corner of the quilt top and trim the horizontal border strip as shown. Repeat to press and trim both ends of each border strip. Note: Be sure to pull the perpendicular strip out of the way each time before cutting.
- 6. With the border strips RST, sew along the angled edge, then press. Repeat for each corner of the quilt. The quilt top should measure $38" \times 57"$.




FINISHING INSTRUCTIONS

7. Finish the quilt by layering the quilt top, batting, and backing. Baste the quilt layers together and quilt as desired. Sew the Black Ironing Board binding strips together end-to-end. Then bind the trimmed, finished quilt using your favorite binding method.

Enjoy your Press On Panel quilt! Share your quilt using the hashtags: #pressonfabric, #pressonpanelquilt, #rileyblakedesigns, #iloverileyblake

QUILT LAYOUT DIAGRAM



38" × 57"