



How to Create a Windows 11 USB Installer

Follow this comprehensive step-by-step guide to create a bootable Windows 11 USB installer. This process will allow you to install or upgrade Windows 11 on any compatible computer using a simple USB flash drive.

Step 1: Prepare Your USB Drive

USB Requirements

Use a USB flash drive with at least 8 GB of free space for the Windows 11 installation files.

Connection

Plug the USB drive into an available USB port on your computer before proceeding.

⚠ Important: All data on the USB drive will be erased during this process. Back up any important files before continuing.



Step 2: Download the Windows 11 Media Creation Tool

01

Navigate to Microsoft's Official Page

Open your web browser and go to the official Microsoft Windows 11 download page: <https://www.microsoft.com/software-download/windows11>

02

Download the Tool

Click on **Download now** under the "Create Windows 11 Installation Media" section to begin downloading the Media Creation Tool.




Step 3: Run the Media Creation Tool

Launch the Application

Locate the downloaded file named `MediaCreationToolW11.exe` in your Downloads folder and double-click it to run the application.

Accept License Terms

When prompted, accept the license terms by clicking **Accept** to proceed with the installation media creation process.



 You may need administrator privileges to run this tool. Click "Yes" if prompted by User Account Control.

language and edition

one of the available options to continue.

English (United States)

Windows 11


Step 4: Choose Installation Media

Select Media Creation Option

Choose **Create installation media** (USB flash drive, DVD, or ISO file) for another PC from the available options.

Continue Process

Click **Next** to proceed to the language and edition selection screen.



Step 5: Select Language, Edition, and Architecture



Language Selection

Choose your preferred **Language** from the dropdown menu. This will determine the language of your Windows 11 installation.



Edition Choice


Select the **Edition** of Windows 11 you want to install (typically Windows 11 Home or Pro).



Architecture Type

Choose the **Architecture** - usually 64-bit (x64) for modern computers. Click **Next** when ready.

Step 6: Choose USB Flash Drive



Select Media Type

Choose **USB flash drive** as the media type to use for creating your Windows 11 installer.

Proceed to Drive Selection

Click **Next** to continue to the USB drive selection screen where you'll choose your specific drive.

Step 7: Select Your USB Drive


Identify Your Drive

Choose your USB drive from the list of available drives. Make sure you select the correct drive to avoid accidentally erasing important data.

Confirm Selection

Double-check that you've selected the right USB drive, then click **Next** to begin the download and creation process.

⊗ **Warning:** All existing data on the selected USB drive will be permanently deleted during this process.




Step 8: Download and Create Installer


Automated Process

The Media Creation Tool will now download Windows 11 installation files and create the USB installer automatically. This process includes:

- Downloading Windows 11 files from Microsoft servers
- Formatting your USB drive
- Creating the bootable installer
- Verifying the installation media



i This process typically takes 30-60 minutes depending on your internet connection speed. Be patient and don't disconnect the USB drive.



Final Steps: Complete and Use Your Installer

Step 9: Finish and Eject

When the creation process completes, click **Finish** in the Media Creation Tool. Then safely eject your USB drive using the system tray icon or file explorer.

1

2

Step 10: Use the USB Installer

Insert the USB installer into the PC where you want to install Windows 11. Restart the computer and boot from the USB drive. You may need to change the boot order in BIOS/UEFI settings.

Congratulations! Your Windows 11 USB installer is now ready to use for installing or upgrading Windows 11 on any compatible computer.