Western Laboratories.com

211 Highway 95 • Parma, ID 83660 800-658-3858 • FAX 208-402-5303 http://www.westernlaboratories.com



Date: 1/8/2020 Client: 11-111 Lab Number

Gardner: Western Labs

Garden ID:

ATLANTIC GIANT PUMPKIN 75S REPORT

EXTRACTABLE NUTRIENTS					SOIL SOLUTION TEST***			
ELEMENT	YOURS	SHOULD BE	RECS**	PRE-PLANT SUGGESTIONS	ELEMENT	YOURS	SHOULD BE	ADD ** WEEKLY
			LBS	LBS			LBS / DAY	LBS
Phosphorus-ppm	97	25 - 40	1	1	P-lbs	1.6	2	0.06
Potassium-ppm	559	300 +			K-lbs	10.1	15	0.45
Calcium-ppm	2304	1,800 +	*		Ca-lbs	4.8	9	*
Magnesium-ppm	479	250 +			Mg-lbs	2.2	2	
			OZ	OZ			grams/DAY	Grams
Zinc-ppm	2.7	1.0 - 3.0	2	1	Zn-grams	68	85	1.34
Copper-ppm	2.8	0.8 - 2.5			Cu-grams	54	56	0.16
Manganese-ppm	12	6 - 30	0	0	Mn-grams	34	85	4.05
Boron-ppm	0.8	0.8 - 1.2	.4		B-grams	28	28	

^{*} Refer to soil report for Calcium recommendations, if needed.

***Our soil solution test emulates the exudates that plant roots release to stimulate bacteria and fungi to release nutrients from the extractable nutrients.

All chelating products can be used if the zinc, copper and magnesium are adequate. When the levels are below the should be levels, you need to use the elements in the sulfate forms. Disease suppressions are caused by the elements in their metallic forms. Chelates are an excellent sources for plant and production needs.

PRE-PLANT:

For disease suppression add 1/2 of the weekly recommendations for all micro nutrients in a sulfate or water soluble oxide in calcareous soils.

For plant needs and maximum bulking add the other 1/2 in chelate form by using the SV (Secret Vault) program to monitor weekly requirements.

1. If no lime and calcium is less than 1800 and soil solution is less than "should be" add 20 lbs. per 1000 sq.ft. of gypsum pre-plant.

If phosphate, potash and magnesium in soil solution are less than requires consider putting field on the SV Program to monitor it. If you are using the SV program and the phosphate, potash, and magnesium "should be" levels in the soil solution are higher than results on the SV Program, it is because the sample is taken with out the influence of the root system. In season results are lower because plant root gives off carbonaceous exodates.

^{**} Recommendations in amount per 1000 sq.ft.