# **Basics for Handling Food Safely**

- Shopping
- Storage
- Preparation
- Thawing
- Cooking
- Serving
- Leftovers
- Refreezing
- Cold Storage Chart

Safe steps in food handling, cooking, and storage are essential to prevent foodborne illness. You can't see, smell, or taste harmful bacteria that may cause illness. In every step of food preparation, follow the four steps of the Food Safe Families campaign to keep food safe:

- Clean Wash hands and surfaces often.
- Separate Don't cross-contaminate.
- Cook Cook to the right temperature.
- Chill Refrigerate promptly.

# **Shopping**

- Purchase refrigerated or frozen items after selecting your non-perishables.
- Never choose meat or poultry in packaging that is torn or leaking.
- Do not buy food past "Sell-By," "Use-By," or other expiration dates.

# [Top of Page]

#### Storage

- Always refrigerate perishable food within 2 hours—1 hour when the temperature is above 90 °F (32.2 °C).
- Check the temperature of your refrigerator and freezer with an appliance thermometer. The refrigerator should be at 40 °F (4.4 °C) or below and the freezer at 0 °F (-17.7 °C) or below.
- Cook or freeze fresh poultry, fish, ground meats, and variety meats within 2 days; other beef, veal, lamb, or pork, within 3 to 5 days.
- Perishable food such as meat and poultry should be wrapped securely to maintain quality and to prevent meat juices from getting onto other food.
- To maintain quality when freezing meat and poultry in its original package, wrap the package again with foil or plastic wrap that is recommended for the freezer.

• Canned foods are safe indefinitely as long as they are not exposed to freezing temperatures, or temperatures above 90 °F. If the cans look ok, they are safe to use. Discard cans that are dented, rusted, or swollen. High-acid canned food (tomatoes, fruits) will keep their best quality for 12 to 18 months; low-acid canned food (meats, vegetables) for 2 to 5 years.

# [Top of Page]

## **Preparation**

- Always wash hands with warm water and soap for 20 seconds before and after handling food.
- Don't cross-contaminate. Keep raw meat, poultry, fish, and their juices away from other food. After cutting raw meats, wash cutting board, utensils, and countertops with hot, soapy water.
- Cutting boards, utensils, and countertops can be sanitized by using a solution of 1 tablespoon of unscented, liquid chlorine bleach in 1 gallon of water.
- Marinate meat and poultry in a covered dish in the refrigerator.

#### [Top of Page]

## **Thawing**

- **Refrigerator**: The refrigerator allows slow, safe thawing. Make sure thawing meat and poultry juices do not drip onto other food.
- Cold Water: For faster thawing, place food in a leak-proof plastic bag. Submerge in cold tap water. Change the water every 30 minutes. Cook immediately after thawing.
- Microwave: Cook meat and poultry immediately after microwave thawing.

#### [Top of Page]

#### Cooking

Cook all raw beef, pork, lamb and veal steaks, chops, and roasts to a minimum internal temperature of 145 °F (62.8 °C) as measured with a food thermometer before removing meat from the heat source. For safety and quality, allow meat to rest for at least three minutes before carving or consuming. For reasons of personal preference, consumers may choose to cook meat to higher temperatures.

**Ground meats:** Cook all raw ground beef, pork, lamb, and veal to an internal temperature of 160 °F (71.1 °C) as measured with a food thermometer.

**Poultry:** Cook all poultry to an internal temperature of 165 °F (73.9 °C) as measured with a food thermometer.

## [Top of Page]

## **Serving**

- Hot food should be held at 140 °F (60 °C) or warmer.
- Cold food should be held at 40 °F (4.4 °C) or colder.
- When serving food at a buffet, keep food hot with chafing dishes, slow cookers, and warming trays. Keep food cold by nesting dishes in bowls of ice or use small serving trays and replace them often.
- Perishable food should not be left out more than 2 hours at room temperature—1 hour when the temperature is above 90 °F (32.2 °C).

## [Top of Page]

#### Leftovers

- Discard any food left out at room temperature for more than 2 hours—1 hour if the temperature was above 90 °F (32.2 °C).
- Place food into shallow containers and immediately put in the refrigerator or freezer for rapid cooling.
- Use cooked leftovers within 4 days.
- Reheat leftovers to 165 °F (73.9 °C).

## [Top of Page]

#### Refreezing

Meat and poultry defrosted in the refrigerator may be refrozen before or after cooking. If thawed by other methods, cook before refreezing.

## [Top of Page]

## **Cold Storage Chart**

These short, but safe, time limits will help keep refrigerated food from spoiling or becoming dangerous to eat. Because freezing keeps food safe indefinitely, recommended storage times are for quality only.

Cold Storage Chart				
Product	Refrigerator 40 °F (4.4 °C)	Freezer 0 °F (-17.7 °C)		
Eggs				
Fresh, in shell	3 to 5 weeks	Do not freeze		
Raw yolks & whites	2 to 4 days	1 year		

Hard cooked	1 week	Does not freeze well		
Liquid pasteurized eggs, egg substitutes				
Opened	3 days	Does not freeze well		
Unopened	10 days	1 year		
Mayonnaise, Comm	ercial			
Refrigerate after opening	2 months	Do not freeze		
Frozen Dinners & Entrees				
Keep frozen until ready to heat	_	3 to 4 months		
Deli & Vacuum-Packed Products				
Store-prepared (or homemade) egg, chicken, ham, tuna, & macaroni salads	3 to 5 days	Does not freeze well		
Hot dogs & Luncheon	n Meats			
Hot dogs				
Opened package	1 week	1 to 2 months		
Unopened package	2 weeks	1 to 2 months		
Luncheon meat				
Opened package	3 to 5 days	1 to 2 months		
Unopened package	2 weeks	1 to 2 months		
Bacon & Sausag	ge			
Bacon	7 days	1 month		
Sausage, raw — from chicken, turkey, pork, beef	1 to 2 days	1 to 2 months		
Smoked breakfast links, patties	7 days	1 to 2 months		
Hard sausage — pepperoni, jerky sticks	2 to 3 weeks	1 to 2 months		
Summer sausage labeled "Keep Refrigerated"				
Opened	3 weeks	1 to 2 months		
Unopened	3 months	1 to 2 months		

Corned Beef				
Corned beef, in pouch with pickling juices	5 to 7 days	Drained, 1 month		
Ham, canned labeled "Keep Refrigerated"				
Opened	3 to 5 days	1 to 2 months		
Unopened	6 to 9 months	Do not freeze		
Ham, fully cooked				
Vacuum sealed at plant, undated, unopened	2 weeks	1 to 2 months		
Vacuum sealed at plant, dated, unopened	"Use-By" date on package	1 to 2 months		
Whole	7 days	1 to 2 months		
Half	3 to 5 days	1 to 2 months		
Slices	3 to 4 days	1 to 2 months		
Hamburger, Ground & S	Stew Meat			
Hamburger & stew meat	1 to 2 days	3 to 4 months		
Ground turkey, veal, pork, lamb, & mixtures of them	1 to 2 days	3 to 4 months		
Fresh Beef, Veal, Lamb, Pork				
Steaks	3 to 5 days	6 to 12 months		
Chops	3 to 5 days	4 to 6 months		
Roasts	3 to 5 days	4 to 12 months		
Variety meats — tongue, liver, heart, kidneys, chitterlings	1 to 2 days	3 to 4 months		
Pre-stuffed, uncooked pork chops, lamb chops, or chicken breasts stuffed with dressing	1 day	Does not freeze well		
Soups & Stews Vegetable or meat added	3 to 4 days	2 to 3 months		
Fresh Poultry				

Chicken or turkey, whole	1 to 2 days	1 year		
Chicken or turkey, pieces	1 to 2 days	9 months		
Giblets	1 to 2 days	3 to 4 months		
Cooked Meat and Poultry Leftovers				
Cooked meat & meat casseroles	3 to 4 days	2 to 3 months		
Gravy & meat broth	3 to 4 days	2 to 3 months		
Fried chicken	3 to 4 days	4 months		
Cooked poultry casseroles	3 to 4 days	4 to 6 months		
Poultry pieces, plain	3 to 4 days	4 months		
Poultry pieces in broth, gravy	3 to 4 days	6 months		
Chicken nuggets, patties	3 to 4 days	1 to 3 months		
Other Cooked Leftovers				
Pizza, cooked	3 to 4 days	1 to 2 months		
Stuffing, cooked	3 to 4 days	1 month		